

Data Model - CONVERSION

Kernel 11.4

[January] [2012]

**ORACLE**<sup>®</sup>  
FINANCIAL SERVICES

# Table Of Contents

---

<b>1. INTRODUCTION</b>	.....	<b>1</b>
<b>2. CONVERSION</b>	.....	<b>2</b>
2.1. CVTM_DATA_ENRICHMENT	.....	2
2.2. CVTM_TMPL_FIELD_MAP	.....	2
2.3. CVTM_TMPL_GROUP	.....	2
2.4. CVTM_TMPL_MASTER	.....	2
2.5. CVTM_TRANSLATION	.....	3
2.6. CVTM_TRANSLATION_TYPE	.....	3
2.7. CVTM_UPLD_TRANSLATION	.....	3

## 1. INTRODUCTION

This document contains the data dictionary information of CONVERSION in Kernel 11.4 . For each table that belongs to the module, CV, it provides the following information

- Table Description
- Primary Key and Foreign Keys
- Column details that contain column name, data type and descriptions.

## 2. CONVERSION

### 2.1. CVTM\_DATA\_ENRICHMENT

**Description** - This is the primary table for the Data Enrichment

**Primary Key and Foreign Keys** -

<b>Primary Key</b>	PRIMARYKEY
--------------------	------------

**Column Descriptions** -

COLUMN	DATA TYPE	DESCRIPTION
PRIMARYKEY	NUMBER	Primary Key
SOURCE_CODE	VARCHAR2(15)	Source Code
MODULE	VARCHAR2(2)	Module Code
GROUP_ID	VARCHAR2(20)	Group ID
TEMPLATE_ID	VARCHAR2(20)	Template ID
TABLE_NAME	VARCHAR2(105)	Table Name
END_RESULT_NAME	VARCHAR2(105)	End Result Name
SOURCE_OR_LITERAL	CHAR(1)	Source /Literal
END_RESULT_VAL	VARCHAR2(105)	End Result Value
END_RESULT_DATATYPE	CHAR(1)	End Result Datatype
EXPRESSION	LONG	Expression
RECORD_STAT	CHAR(1)	Record Status
AUTH_STAT	CHAR(1)	Auth Status
ONCE_AUTH	CHAR(1)	Once Auth
MOD_NO	NUMBER(4)	Modification Number
MAKER_ID	VARCHAR2(12)	Input By
CHECKER_ID	VARCHAR2(12)	Authorised By

### 2.2. CVTM\_TMPL\_FIELD\_MAP

**Description** - This is the table for the Template Field Mapping

**Primary Key and Foreign Keys** - **Column Descriptions** -

COLUMN	DATA TYPE	DESCRIPTION
GROUP_ID	VARCHAR2(20)	Group ID
TEMPL_ID	VARCHAR2(20)	Template ID
STAGE	CHAR(1)	Stage
SOURCE_FIELD_NAME	VARCHAR2(50)	Source Field Name
DEST_FIELD_NAME	VARCHAR2(50)	Destination Field Name
TRANS_TYPE	VARCHAR2(20)	Translation Type
DTYPE	CHAR(1)	Data Type

### 2.3. CVTM\_TMPL\_GROUP

**Description** - This is the primary table for the Template Group Code

**Primary Key and Foreign Keys** - **Column Descriptions** -

COLUMN	DATA TYPE	DESCRIPTION
GROUP_ID	VARCHAR2(20)	Group ID
GROUP_DESC	VARCHAR2(100)	Group Description
SOURCE_CODE	VARCHAR2(105)	Source Code
MODULE_CODE	CHAR(2)	Module Code
INT_TO_UPL_FNAME	VARCHAR2(100)	Interface Field Name
UPL_TO_CUBE_FNAME	VARCHAR2(100)	Flexcube Field Name
RECORD_STAT	CHAR(1)	Record Status
AUTH_STAT	CHAR(1)	Auth Status

ONCE_AUTH	CHAR(1)	Once Auth
MOD_NO	NUMBER(4)	Modification Number
MAKER_ID	VARCHAR2(12)	Input By
CHECKER_ID	VARCHAR2(12)	Authorised By

## 2.4. CVTM\_TMPL\_MASTER

**Description** - This is the primary table for the Template Code Miantenance

**Primary Key and Foreign Keys - Column Descriptions -**

COLUMN	DATA TYPE	DESCRIPTION
GROUP_ID	VARCHAR2(20)	Group ID
TEMPL_ID	VARCHAR2(20)	Template ID
SEQUENCE_NO	NUMBER(2)	Sequence Number
INMDT_TABLE_NAME	VARCHAR2(100)	Intermediate Table Name
UPLD_TABLE_NAME	VARCHAR2(100)	Upload Table Name
CUBE_TABLE_NAME	VARCHAR2(100)	Cube Table Name

## 2.5. CVTM\_TRANSLATION

**Description** - This is the table for Translation Details for Interface

**Primary Key and Foreign Keys -**

<b>Primary Key</b>	SOURCE_CODE,TRANSLATION_TYPE,EXTERNAL_BRANCH,EXTERNAL_VALUE,INTERNAL_VALUE
--------------------	--

**Column Descriptions -**

COLUMN	DATA TYPE	DESCRIPTION
SOURCE_CODE	VARCHAR2(15)	Source Code
TRANSLATION_TYPE	VARCHAR2(15)	Translation Type
EXTERNAL_BRANCH	VARCHAR2(105)	External Branch
EXTERNAL_VALUE	VARCHAR2(105)	External Value
INTERNAL_BRANCH	VARCHAR2(3)	Flexcube Branch
INTERNAL_VALUE	VARCHAR2(105)	Flexcube Value

## 2.6. CVTM\_TRANSLATION\_TYPE

**Description** - This is the primary table for the FLEXCUBE Translation Type Maintenance

**Primary Key and Foreign Keys -**

<b>Primary Key</b>	SOURCE_CODE,TRANSLATION_TYPE
--------------------	------------------------------

**Column Descriptions -**

COLUMN	DATA TYPE	DESCRIPTION
SOURCE_CODE	VARCHAR2(15)	Source Code
TRANSLATION_TYPE	VARCHAR2(15)	Translation Type
BRANCH_REQUIRED	CHAR(1)	Branch Required
RECORD_STAT	CHAR(1)	Record Status
AUTH_STAT	CHAR(1)	Auth Status
ONCE_AUTH	CHAR(1)	Once Auth
MAKER_ID	VARCHAR2(12)	Input By
CHECKER_ID	VARCHAR2(12)	Authorised BY
MOD_NO	NUMBER(4)	Modification Number
TAKE_CUBE_VALUE	CHAR(1)	Flexcube Value

## 2.7. CVTM\_UPLD\_TRANSLATION

**Description** - This is the table for the Translation Details For Upload

**Primary Key and Foreign Keys** -

<b>Primary Key</b>	MAINTENANCE_SEQ_NO,SOURCE_CODE,TRANSLATION_TYPE,EXTERNAL_BRANCH,EXTERNAL_VALUE,INTERNAL_VALUE
--------------------	---

**Column Descriptions** -

<b>COLUMN</b>	<b>DATA TYPE</b>	<b>DESCRIPTION</b>
MAINTENANCE_SEQ_NO	VARCHAR2(16)	Maintenance Sequence Number
SOURCE_CODE	VARCHAR2(15)	Source Code
TRANSLATION_TYPE	VARCHAR2(15)	Translation Type
EXTERNAL_BRANCH	VARCHAR2(105)	External Branch
EXTERNAL_VALUE	VARCHAR2(105)	External Code
INTERNAL_BRANCH	VARCHAR2(3)	Flexcube Branch
INTERNAL_VALUE	VARCHAR2(105)	Flexcube Value
ACTION_CODE	VARCHAR2(6)	Action Code
SOURCE_SEQ_NO	NUMBER	Source Sequence Number
BRANCH_CODE	VARCHAR2(3)	Branch Code



**CONVERSION**

[January] [2012]

Oracle Corporation  
World Headquarters  
500 Oracle Parkway  
Redwood Shores, CA 94065  
U.S.A.

**Worldwide Inquiries:**

**Phone: +1.650.506.7000**

**Fax: +1.650.506.7200**

**[www.oracle.com/ financial\\_services/](http://www.oracle.com/financial_services/)**

**Copyright © [2012] Oracle Financial Services Software Limited. All rights reserved.**

**No part of this work may be reproduced, stored in a retrieval system, adopted or transmitted in any form or by any means, electronic, mechanical, photographic, graphic, optic recording or otherwise, translated in any language or computer language, without the prior written permission of Oracle Financial Services Software Limited.**

**Due care has been taken to make this document and accompanying software package as accurate as possible. However, Oracle Financial Services Software Limited makes no representation or warranties with respect to the contents hereof and shall not be responsible for any loss or damage caused to the user by the direct or indirect use of this document and the accompanying Software System. Furthermore, Oracle Financial Services Software Limited reserves the right to alter, modify or otherwise change in any manner the content hereof, without obligation of Oracle Financial Services Software Limited to notify any person of such revision or changes.**

**All company and product names are trademarks of the respective companies with which they are associated.**